Installation and first activation

For the server administrator · Fresh installation on Linux x86_64 with Docker Compose. One activation covers the installation and all its users.

1 Before running the installer

Open START-HIER.html. Find the archive and its .sha256 file in 00_Installation. Verify the checksum and prepare Linux, DNS, HTTPS certificates and credentials according to the installation manual. Have the Medlix purchase code issued for this installation ready.

2 Complete installation

After configure and install, ACTIVATION_REQUIRED is an expected result. Open the configured Uptime HTTPS address in your browser. The business application starts after the license passes verification.



3 With internet access

Enter the purchase code in Kaufcode and choose Online aktivieren (activate online). The server needs HTTPS access to lizenz.medlix.de. Wait for confirmation and application startup, then sign in with the account created during setup and configure MFA.

First activation on an isolated network

The Uptime server stays on the internal network. Only the second device needs internet access. Activation requires neither a file transfer nor terminal commands.

1 Open the request in Uptime

Enter the purchase code and select Mit QR-Code aktivieren (activate using QR). Treat the QR code as confidential. It contains the purchase code and the signed request for this installation.



Illustration with fictitious data. Scan the QR code on your own server screen.

2 Confirm on the second device

Scan with the camera, check that the HTTPS address is lizenz.medlix.de and confirm activation on the Medlix page. Copy or transcribe the entire grouped confirmation code.

3 Apply the grant locally

On the original Uptime screen enter it in Freischaltcode and select Freischaltung bestätigen (confirm activation). Sign in once Uptime is ready.

Operations, recovery and troubleshooting

Activation and user accounts

The grant belongs to the server installation. Create accounts and assign permissions as described in the administrator manual. Business screens, APIs and background processing are locked before activation. Provision integration API access separately if required.

Restart and backup

An activated perpetual license works after a restart while the license service is offline. Preserve the persistent /keys directory when recreating the container. A complete Uptime backup includes the installation identity. Encrypt backups, restrict access and verify restoration on an isolated target.

Occupied seat or invalid confirmation code

Confirm that the purchase code was issued for this Uptime installation. For a replacement server, check the existing backup and coordinate the transfer with Medlix. For an invalid offline confirmation, check the complete code and use the installation that created the request. Keep purchase codes, QR codes and private keys out of support messages.

Acceptance and existing installations

After activation, verify MFA login, permissions and a synthetic sample report. Use an empty target for a fresh install. Coordinate preactivation and cutover with Medlix for existing installations. Replacing a single application container takes restart time.

This edition combines the R3 business application with a license gate. Earlier statements about image identity with the previous server and immediate first login refer to the previous delivery. Use the release identity and checksums supplied in this package.